

```

; =====
; geoGopher.inc: include file for geoGopher
; =====
NUM_MODS    =      8            ;highest module no.
MOD_CFG     =      1            ;module no. for setup code
MOD_ULT     =      3            ;module no. for Ultimate network driver
MOD_FONT    =      8            ;module no. for small font
SCR_SAVE    =      1            ;for manual screen buffering
SCR_RSTR    =      2
BUFSIZE     =     257
BUF_END     =     $c0            ;return values for getItem
BUF_OVFL    =     $c1
BUF_EMPTY   =     $c2
TYP_TEXT    =      '0'          ;gopher item types
TYP_FLDR    =      '1'
TYP_ERR     =      '3'
TYP_SRCH    =      '7'
TYP_BIN     =      '9'
TYP_INFO    =      'i'
TYP_UNKN    =     255            ;unknown/unsupported
NUM_TYPE    =      7            ;number of supported types
MAX_HOST    =     30            ;maximum length of a hostname
MAX_SEL     =     128            ;maximum length of a selector
BACKSIZE    =     (MAX_HOST+1)+(MAX_SEL+3)+6
                                     ;3 for itemType/topItem, 6 for port
MAX_BACK    =      3            ;size of back stack
; =====
ITEM_Y_1    =     18            ;top edge of first item icon
ITEM_HI     =     24            ;height of a gopher item
ITEM_WD     =     67            ;max. char width of item
ITXT_X      =     36            ;left edge of text beside icons
; =====
TXT_INFO    =      0
TXT_FILE    =      1
TEXT_TOP    =     13            ;top of text/info (vwTextDB)
TEXT_L      =      7            ;left margin for text
TEXT_WD     =     74            ;max chars. across (vwTextDB)
MAX_LINE    =     22            ;max. lines of text on a page
MAX_PAGE    =     32            ;max. pages
; =====
STATUS_T    =     187
THUMB_HI    =     16
THUMB_WD    =      5
THUMBMIN    =      8
; =====
; IDs for custom DB icons
; =====
CREATE      =     101
QUIT        =     102
SAVE        =     103
DELETE      =     104
EDIT        =     105
DRIVE       =     106
VIEW        =     107
CLOSE       =     108
; =====
; custom error IDs
; =====
NOT_CVT     =     200            ;not a .CVT file
DL_ERR      =     201            ;download error
CVTLNERR    =     202            ;length error (CVT header)
HDLNERR     =     203            ;length error (file header)
VLRNERR     =     204            ;length error (VLIR index)
VBKLNERR    =     205            ;length error (VLIR data block)
CNCL_ERR    =     206            ;operation canceled
MEM_ERR     =     207            ;out of memory

```